

CSC 524

Computer Networks Dr. Esam A. Alwagait

Lecture 4 18-19/2/2013

Agenda

- 1 Introduction
- 2 Data Link Layer Design Issues
- 3 Error Detection and Correction
- 4 Data Layer Protocols
- 5 Sliding Window Protocols
- 6 Summary & Discussion



Introduction



- Last week we discussed Physical Layer
- How do you send data from Network Layer to Physical layer?
- How do you detect errors?
 - Or Correct them ?
- Examples of Protocols for sender and receivers.
- And more!



Agenda


- 1 Introduction
- 2 Data Link Layer Design Issues
- 3 Error Detection and Correction
- 4 Data Layer Protocols
- 5 Sliding Window Protocols
- 6 Summary & Discussion



Design Issues




- Functions of Data Link Layer:
 - Providing a well-defined service interface to the network layer.
 - Dealing with transmission errors.
 - Regulating the flow of data
 so that slow receivers are
 not swamped by fast
 senders.







- Data Link Layer (DL) Takes packets from network layer and transmits them in Frames
- Each frame has a header and a Trailer





- Notice: many of the issues we will discuss can be found in other layers too. regardless, It is the concept that matters rather than the place where the functionality is implemented.
- Three services that are commonly provided are:
 - Unacknowledged connectionless service.
 - Acknowledged connectionless service.
 - Acknowledged connection-oriented service.






- Unacknowledged connectionless
 - No ack
 - No Error detection/correction
 - Assumption of a reliable channel
- acknowledged connectionless
 - Ack is used to determain reliable sending
- Connection-oriented acknowledged
 - Several frames are sent within a "channel"





Framing - Character Counting!




A character stream. (a) Without errors. (b) With one error.





Framing - Flags




- (a) A frame delimited by flag bytes.
- (b) Four examples of byte sequences before and after stuffing.





- Byte stuffing assumes 8bit characters
 - UNICODE is 16 bit
 - Bit stuffing (0111110)



- (c) 011011111111111111110010
- Bit stuffing
- (a) The original data.
- (b) The data as they appear on the line.
- (c) The data as they are stored in receiver's memory after destuffing.





- Error Control
 - Detection
 - Correction
- Flow Control
 - What if the sender is too Fast!
 - Feedback-based Flow control
 - Rate-based flow control
 - We will discuss them in future lectures



Agenda

- 1 Introduction
- 2 Data Link Layer Design Issues
- 3 Error Detection and Correction
- 4 Data Layer Protocols
- 5 Sliding Window Protocols
- 6 Summary & Discussion





- Error control deals with problems that could occur in the physical layer!
- Must include redundant data!
 - How much? Depends on the choice
- A choice has to be made whether to correct or just detect!
 - Detect requires re-transmission
 - Correction introduces extra cost
- Wireless is usually noisy, LAN is not!





Error Correction


- Hamming Distance
 - Codeword is Message (m) + Redundant (r)
 - if two codewords are a Hamming distance d apart, it will require d single-bit errors to convert one into the other.
 - i.e you could reverse the error
 - Introducing Parity bit(s) (even/odd)
 - Single even parity bit
 - E.g. 1011010 becomes 10110100
 - Odd is 10110101






- Parity bits are in positions of the 2(n)
- E.g. 3 parity bits

765432	2 1	
DDDPDI	P 7-BIT CODEWOR	D
	P (EVEN PARITY)	
	P - (EVEN PARITY)	
DDDP-	- (EVEN PARITY)	










7654321		
1110110	7-BIT CODEWORD	
1-1-1-0	(EVEN PARITY)	NOT! 1
1111-	(EVEN PARITY)	OK! 0
1110	(EVEN PARITY)	NOT! 1



- 101 = 5 .. Bit 5 is wrong! Reverse it
- Same principle for larger number of bits
- http://www.ee.unb.ca/tervo/ee4253/hamming. shtml





Error detection

- Error correction sometimes introduces an extra overhead that is not justified!
- Bandwidth is consumed to send error correction data more than the data itself
- The % of r/m !
- If the error probability is not high, it is easier to retransmit





- How do you detect an error?
 - Checksum!
 - Polynomial code → CRC (Cyclic Redundancy Check)
- Sender and receiver must agree on a Generator Function G(x)
- Checksums are used in other applications like storing passwords



Agenda

- 1 Introduction
- 2 Data Link Layer Design Issues
- 3 Error Detection and Correction
- 4 Data Layer Protocols
- 5 Sliding Window Protocols
- 6 Summary & Discussion



Data Layer Protocol



```
#define MAX PKT 1024
                                                /* determines packet size in bytes */
typedef enum {false, true} boolean;
                                                /* boolean type */
typedef unsigned int seg nr;
                                                /* sequence or ack numbers */
typedef struct {unsigned char data[MAX_PKT];} packet;/* packet definition */
                                                /* frame kind definition */
typedef enum {data, ack, nak} frame_kind;
typedef struct {
                                                /* frames are transported in this layer */
 frame_kind kind;
                                                /* what kind of a frame is it? */
                                                /* sequence number */
 seq_nr seq;
                                                /* acknowledgement number */
 seq_nr ack;
 packet info;
                                                /* the network layer packet */
} frame;
```





```
/* Wait for an event to happen; return its type in event. */
void wait for event(event type *event);
/* Fetch a packet from the network layer for transmission on the channel. */
void from network layer(packet *p);
/* Deliver information from an inbound frame to the network layer. */
void to_network_layer(packet *p);
/* Go get an inbound frame from the physical layer and copy it to r. */
void from physical layer(frame *r);
/* Pass the frame to the physical layer for transmission. */
void to_physical_layer(frame *s);
/* Start the clock running and enable the timeout event. */
void start timer(seg nr k);
/* Stop the clock and disable the timeout event. */
void stop_timer(seq_nr k);
/* Start an auxiliary timer and enable the ack_timeout event. */
void start_ack_timer(void);
/* Stop the auxiliary timer and disable the ack_timeout event. */
void stop ack timer(void);
/* Allow the network layer to cause a network_layer_ready event. */
void enable_network_layer(void);
/* Forbid the network layer from causing a network layer ready event. */
void disable network layer(void);
/* Macro inc is expanded in-line: Increment k circularly. */
#define inc(k) if (k < MAX\_SEQ) k = k + 1; else k = 0
```



```
/* Protocol 1 (utopia) provides for data transmission in one direction only, from
 sender to receiver. The communication channel is assumed to be error free,
 and the receiver is assumed to be able to process all the input infinitely quickly.
 Consequently, the sender just sits in a loop pumping data out onto the line as
 fast as it can. */
typedef enum {frame arrival} event type;
#include "protocol.h"
void sender1(void)
                                    /* buffer for an outbound frame */
 frame s:
 packet buffer;
                                    /* buffer for an outbound packet */
 while (true) {
    from network layer(&buffer); /* go get something to send */
    s.info = buffer;
                                    /* copy it into s for transmission */
    to_physical_layer(&s);
                                    /* send it on its way */
                                     * Tomorrow, and tomorrow, and tomorrow.
                                      Creeps in this petty pace from day to day
                                      To the last syllable of recorded time
                                         - Macbeth, V, v */
```



```
/* Protocol 2 (stop-and-wait) also provides for a one-directional flow of data from
  sender to receiver. The communication channel is once again assumed to be error
  free, as in protocol 1. However, this time, the receiver has only a finite buffer
  capacity and a finite processing speed, so the protocol must explicitly prevent
  the sender from flooding the receiver with data faster than it can be handled. */
typedef enum {frame arrival} event type;
#include "protocol.h"
void sender2(void)
                                      /* buffer for an outbound frame */
 frame s:
                                      /* buffer for an outbound packet */
 packet buffer;
                                      /* frame_arrival is the only possibility */
 event_type event;
 while (true) {
    from_network_layer(&buffer);
                                      /* go get something to send */
     s.info = buffer;
                                      /* copy it into s for transmission */
    to_physical_layer(&s);
                                     /* bye bye little frame */
     wait_for_event(&event);
                                     /* do not proceed until given the go ahead */
void receiver2(void)
 frame r, s;
                                      /* buffers for frames */
 event_type event;
                                     /* frame_arrival is the only possibility */
 while (true) {
     wait_for_event(&event);
                                      /* only possibility is frame_arrival */
    from physical layer(&r);
                                     /* go get the inbound frame */
    to network layer(&r.info);
                                     /* pass the data to the network layer */
                                      /* send a dummy frame to awaken sender */
    to physical layer(&s);
```



```
/* Protocol 3 (par) allows unidirectional data flow over an unreliable channel. */
#define MAX SEQ 1
                                              /* must be 1 for protocol 3 */
typedef enum {frame arrival, cksum err, timeout} event type;
#include "protocol.h"
void sender3(void)
 seg nr next frame to send;
                                              /* seg number of next outgoing frame */
                                              /* scratch variable */
 frame s:
                                              /* buffer for an outbound packet */
 packet buffer;
 event type event;
 next frame to send = 0;
                                              /* initialize outbound sequence numbers */
 from network layer(&buffer);
                                              /* fetch first packet */
 while (true) {
     s.info = buffer:
                                              /* construct a frame for transmission */
     s.seq = next_frame_to_send;
                                              /* insert sequence number in frame */
                                              /* send it on its way */
     to_physical_layer(&s);
     start timer(s.seq);
                                              /* if answer takes too long, time out */
                                              /* frame_arrival, cksum_err, timeout */
     wait_for_event(&event);
     if (event == frame arrival) {
          from physical layer(&s);
                                              /* get the acknowledgement */
          if (s.ack == next_frame_to_send) {
               stop_timer(s.ack);
                                              /* turn the timer off */
               from_network_layer(&buffer); /* get the next one to send */
               inc(next frame to send);
                                              /* invert next frame to send */
```



```
void receiver3(void)
 seq_nr frame_expected;
 frame r, s;
 event type event;
 frame_expected = 0;
 while (true) {
     wait_for_event(&event);
                                              /* possibilities: frame arrival, cksum err */
                                              /* a valid frame has arrived. */
     if (event == frame_arrival) {
          from_physical_layer(&r);
                                              /* go get the newly arrived frame */
          if (r.seq == frame expected) {
                                              /* this is what we have been waiting for. */
               to_network_layer(&r.info);
                                              /* pass the data to the network layer */
               inc(frame expected);
                                              /* next time expect the other sequence nr */
          s.ack = 1 - frame expected;
                                              /* tell which frame is being acked */
          to_physical_layer(&s);
                                              /* send acknowledgement */
```



Sliding window protocol



- Stop-and-wait wastes bandwidth!
- Simplest form of flow control
- In Stop-and-Wait flow control, the receiver indicates its readiness to receive data for each frame

Operations:

- 1. Sender: Transmit a single frame
- 2. Receiver: Transmit acknowledgment (ACK)
- 3. Goto 1.






- Transmission delay = time to send the data
 - E.g. 1000 bit over 1Mbps = 1msec
- Propagation delay = time from a bit is sent till it is received
 - Depends on medium and distance
 - E.g. 1000 km over guided media (200km/sec) is 5 msec











Analysis of Stop-and-Wait

Notation:

C = Channel capacity in bps

I = Propagation delay

H = Number of bits in a frame header

D = Number of data bits in a frame


F = Total length of a frame (F= D+H)

A = Total length of an ACK frame

F/C = Transmission delay for a frame












- Sliding Window Protocol
 - Multiple frames transmitted at a time
 - Sending and receiver both have "windows"
 - Each frame has a sequence number
 - Window have lower+higher bounds
 - When receiving a frame receiver increases lower bound of the window and sends ack to the sender
 - Timeout? Resend
 - Received something out of the window. Drop it





■ Sending Window:

- At any instant, the sender is permitted to send frames with sequence numbers in a certain range
- The range of sequence numbers is called the *sending* window








Receiving Window:


- The receiver maintains a *receiving window* corresponding to the sequence numbers of frames that are accepted














■ Operations at the sender:














Analysis of Sliding Windows








- Two types of errors:
- Lost frames
- Damaged Frames
- Most Error Control techniques are based on (1)
 Error Detection Scheme (e.g., Parity checks, CRC),
 and (2) Retransmission Scheme
- Error control schemes that involve error detection and
- retransmission of lost or corrupted frames are referred to as Automatic Repeat Request (ARQ) error control











 Go-Back-N uses the sliding window flow control protocol. If no errors occur the operations are identical to Sliding Window

Operations:

- A station may send multiple frames as allowed by the window size
- Receiver sends a NAK i if frame i is in error. After that, the receiver discards all incoming frames until the frame in error was correctly retransmitted
- If sender receives a NAK i it will retransmit frame i and all packets i+1, i+2,... which have been sent, but not been acknowledged



THANK YOU!